

APS Manager Module OUTPUT Version 1.1

How to install it ?

That plugin could be added on your APS Manager for Control-M, since version 3.9.

Prerequisites:

- OUTPUT share must be created and APS Manager server must have rights to access on
- OUTPUT folder must have enough rights to save all output from Control-M

Here are steps to install it:

- Download module from [following link](#)
- Extract Module content in your APS Manager installation, copying all files in .../www/modules folder
- Create symbolic link with .../www/modules/output/output folder with OUTPUT share.
- Open APS Manager browser and provide rights to users

Module Extraction

Module must be explode in following folder : **[APS Home installation]/www/modules/output**

Example : E:\Apsm\ww\modules\output

Create Symbolic Link

Folder : **[APS Home installation]/www/modules/output/output**

Must be replace by Symbolink link to access on share folder where all output were be saved.

Example :

mklink /D E:\Apsm\www\modules\output\output \\servername\OUTPUT_Share

Provide user rights to access on

You must be APS Manager admin, to manage User Rights in APS Manager.

When OUTPUT Module will be deployed on APS Manager folder, module will appear in

Module : Output	No access ▼
-----------------	-------------

Choose right you want to apply

No access
▼

Administrator access


Read / Write access

Read only access

No access

Best practice

The best is to create every days in OUTPUT share, a folder having ODATE, and save output you need to keep in that folder



The screenshot displays the APS Manager Console interface. On the left, a tree view shows the 'output' folder structure. The main pane shows a table of files with columns: Nom, Permissions, Modifié, Taille, and Type. A terminal window is open, showing the execution of a job named 'PCTMTA_ID_020_FLOW_3R'. The job log includes the start time, host information, connection details, and the successful completion of a file transfer.

Nom	Permissions	Modifié	Taille	Type
PCTMTA_PFR01_010_CHECK-STORES_19.txt	Lecture et Ecriture	Aujourd'hui 17:20	314 KB	Texte non formaté
PCTMTA_PFR03_010_CHECK-STORES_20.txt	Lecture et Ecriture	Aujourd'hui 16:55	44 KB	Texte non formaté
PCTMTA_PFR03_010_CHECK-STORES_19.txt	Lecture et Ecriture	Aujourd'hui 16:54	44 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_18.txt	Lecture et Ecriture	Aujourd'hui 16:51	313 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_17.txt	Lecture et Ecriture	Aujourd'hui 16:19	314 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_16.txt	Lecture et Ecriture	Aujourd'hui 15:50	314 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_15.txt	Lecture et Ecriture	Aujourd'hui 15:21	315 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_14.txt	Lecture et Ecriture	Aujourd'hui 14:50	316 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_13.txt	Lecture et Ecriture	Aujourd'hui 14:18	314 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_12.txt	Lecture et Ecriture	Aujourd'hui 13:49	314 KB	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_11.txt	Lecture et Ecriture	Aujourd'hui 13:48	666 b	Texte non formaté
PCTMTA_PFR01_010_CHECK-STORES_10.txt	Lecture et Ecriture	Aujourd'hui 12:55	315 KB	Texte non formaté
PCTMTA_PFR03_010_CHECK-STORES_09.txt	Lecture et Ecriture	Aujourd'hui 12:31	71 b	Texte non formaté
PCTMTA_PFR03_010_CHECK-STORES_08.txt	Lecture et Ecriture	Aujourd'hui 12:19	71 b	Texte non formaté

```

Job started at '0830 13:48:41:041' orderno - 'Igns4' runno - '00001'
Number of transfers - 1
+ Host1 'erp-palupct3'[Unix-SFTP] username 'sentinel' - Host2 'Local'[Windows-Local]
Local host is: ERP-PA1W8BUI7 - Windows 200x [602] build 9200 - Intel64 Family
+ ***** Starting transfer #1 out of 1 *****
Connection to SSH server on host 'erp-palupct3' was established
No matching files for pattern '*.csv'
Transfer #1 completed successfully
Job executed successfully. exiting.
Job ended at '0830 13:48:41:384'
Elapsed time [0sec] CPU usage [0.7sec]
  
```